

## CheckBox Control in VB.NET

Check box control is used to represent a list of options to the user from which the user can select none or any number of options. Check Box control allows the user to select or deselect a particular option. Each time the user clicks on the Check Box, its status gets changed. When a check box is selected, it has a checked status, and when it is not selected, it has an unchecked status.



## Properties of CheckBox Control in VB.NET

Property	Purpose
AutoCheck	It is used to specify whether CheckBox can automatically change its state or not when it is clicked. It has Boolean value. Default value is true.
CheckAlign	It is used to get or set alignment of the <input checked="" type="checkbox"/> within CheckBox Control.
Checked	It is used to get or set Boolean value, which indicates whether CheckBox Control is currently selected or not. It has Boolean value. True means selected. Default value is false.
CheckState	It is used to get or set current state of the CheckBox Control. It can have one of the following three values: Checked, Unchecked, Indeterminate
ThreeState	It is used to specify whether CheckBox Control allows three check states instead of two check states or not. It has a Boolean value. Default value is false.
Text	It is used to get or set text associated with CheckBox Control.
TextAlign	It is used to get or set alignment of the text that is associated with CheckBox Control.
Enabled	It is used to specify whether CheckBox Control is enabled or not. It has Boolean value. Default value is true.
Visible	It is used to specify whether CheckBox Control is visible or not at run

	time.
	It has Boolean value. Default value is true.
BackColor	It is used to get or set background color of the CheckBox.
ForeColor	It is used to get or set color of the text associated with CheckBox.
Font	It is used to get or set font Style, Font Size, Font Face of the text associated with CheckBox.
TabStop	It is used to specify whether user can use TAB key to set focus on CheckBox Control
	or not. It has Boolean value. Default value is true.

## Methods of CheckBox Control in VB.NET

Method	Purpose
Show	It is used to show CheckBox Control at run time.
Hide	It is used to Hide CheckBox Control at run time.
Focus	It is used to set cursor or focus on CheckBox Control.

## Events of CheckBox Control in VB.NET

Event	Purpose
CheckedChanged	It is the default event of CheckBox Control. It fires each time the value
	of checked property is changed.
CheckStateChanged	It fires each time the value of CheckState property is changed.